

```

monitor Bounded_Buffer {
    typeT buf[n];      # an array of some type T
    int front = 0,    # index of first full slot
        rear = 0;    # index of first empty slot
        count = 0;   # number of full slots
    ## rear == (front + count) % n
    cond not_full,    # signaled when count < n
        not_empty;   # signaled when count > 0

    procedure deposit(typeT data) {
        while (count == n) wait(not_full);
        buf[rear] = data; rear = (rear+1) % n; count++;
        signal(not_empty);
    }

    procedure fetch(typeT &result) {
        while (count == 0) wait(not_empty);
        result = buf[front]; front = (front+1) % n; count--;
        signal(not_full);
    }
}

```

Figure 5.4 Monitor implementation of a bounded buffer.